

# How To Install Twitch from VideoCopilot.net into Adobe Premiere CC 2015

Instructions are from Studio 1 Productions, written by David Knarr

**Please Note:** Even though Twitch works in Adobe Premiere, VideoCopilot.net does **NOT** support it's use in Adobe Premiere. If you post question about Twitch on their forum, you may find some members tell you it does not work in Premiere. **However**, it does work.

- 1) Purchase and Download Twitch from [VideoCopilot.net](http://VideoCopilot.net)
- 2) When you download Twitch you will need to unzip it. It will create a folder called **Twitchv1.2**
- 3) Go to **C:\Program Files\Adobe\Common\Plug-ins\7.0\MediaCore**  
Create a folder called **Twitch** in the **MediaCore** folder.
- 4) Go back to the **Twitchv1.2** folder.  
Then go into the **twitch\_ae** folder and you will find a file called **twitch\_ae.key**
- 5) Copy the **twitch\_ae.key** file in to the  
**C:\Program Files\Adobe\Common\Plug-ins\7.0\MediaCore\Twitch** folder.
- 6) Go back into the **Twitchv1.2** folder. Then go into the  
**twitch\_v1.2\_pc\_x86\_x64\Twitch for Windows\64-bit Plugin** folder  
and you will find the file **twitch.aex** file.
- 7) Copy the **twitch.aex** file in to the  
**C:\Program Files\Adobe\Common\Plug-ins\7.0\MediaCore\Twitch** folder.

## Now Twitch is installed in Premiere.

- 8) Next, we will continue with installing the **Twitch Presets** for Premiere.
- 9) You MUST follow these instructions exactly.
- 10) In the same folder as these directions you will find a file called **Twitch.prfpset**
- 11) Copy the **Twitch.prfpset** file in to:  
**C:\Program Files\Adobe\Adobe Premiere Pro CC 2015\Presets** folder.
- 11) Next, you will have to import the Preset into Premiere. Next are the step you need to follow.
- 12) Start up **Premiere** and **Open a Project**.

13) Once the **Premiere Project** loads, look in the bottom left area of the screen. You will see a tab mark **Effects**. Click on the **Effects** tab.

14) **Right Click** on the folder marked **Presets** and then select **Import Preset**.

15) Navigate to the **C:\Program Files\Adobe\Adobe Premiere Pro CC 2015\Presets** folder.

There you will see the Preset file called **Twitch.prfpset** Click on that filename and then select **Open**.

The Presets for Twitch will now be installed.

Twitch will be located under Video Effects as VideoCopilot.